


# Setup and play movie

- [Switch play/pause, move frame forward/backward](#)
- [Play settings](#)


First, open necessary movie (see [here](#) how).





## Switch play/pause, move frame forward/backward

Find on the right program panel the 'Video play' section:




or on the bottom program panel:



- Play/pause the movie:
  - press  button to play or  button to pause;
  - or you can switch on/off movie playback by pressing 'Space' key.
- Go to the next/previous movie frame
  - press  button to move forward or  to move backward;
  - or scroll mouse wheel forward (backward);
  - or press CTRL + LEFT ARROW key combination to move backward or CTRL + RIGHT ARROW to move forward.
- To control movie slider using a mouse press and keep left mouse button and move the mouse.




## Play settings

1. Find 'Video Source' section on 'View' panel:




2. Setup split type, round mode, half time mode, frame rate if necessary:

Parameter	Value	Description
Split type	Mono	Images will be shown as in the initial images stream without any modifications.

	Side by Side (Left first)	<div><p>The initial frame is split by a vertical line into two images intended for the left and the right eye, respectively.</p><p>This is a widespread content type.</p></div>
	Frames Shift (Left first)	<div><p>Images for the left and the right eye produced from initial images stream and shifted initial images stream.</p><p>This split type is suitable for movies with rotating objects.</p></div>
	Over/Under (Left on top)	<div><p>The initial frame is split by a horizontal line into two images intended for the left and the right eye, respectively.</p><p>This is a rare content type.</p></div>
Round	checked or unchecked	Loop or not the movie.
Half Time	checked or unchecked	Play full movie or only the half of it.
FPS	Integer from 1 to 60	Frames rate.

3. To setup stereo mode and switch it on/off, find on the right program panel the "View control" section:



- Select the **Stereo Mode** using the combobox:
  - **Anaglyph** (Red/Blue) - for red-blue stereo glasses;
  - **Interlaced** (Polarized) - for interlaced polarized stereo glasses;
  - **HorizontalAnamorphic** or **Vertical Anamorphic** - for TV via HDMI
  - **Graphics Driver** - for NVIDIA 3D Vision stereo glasses
- Swap Left and Right Frames if necessary using the icon 