

Table obsolete


 This parameter is applicable only to Round brilliant cut.

Table obsolete is an analog to Table outside with the following distinction: first an average direction is taken between the two directions of normals to the opposite bezel facets, and then the width of table is measured along that direction.

Reporting

Reported in	Section	Values	Units	Bookmarks
Full Report for Brilliant	Main Parameters	Avg, Min, Max, Dev	Both %(diameter) and mm	TABLE_OBSOLETE_PC_AVG, TABLE_OBSOLETE_PC_MIN, TABLE_OBSOLETE_PC_MAX, TABLE_OBSOLETE_PC_DEV, TABLE_OBSOLETE_MM_AVG, TABLE_OBSOLETE_MM_MIN, TABLE_OBSOLETE_MM_MAX, TABLE_OBSOLETE_MM_DEV
	Detailed Parameters	All 4 values	Both %(diameter) and mm	TABLE_OBSOLETE_PC_1, ..., TABLE_OBSOLETE_PC_4, TABLE_OBSOLETE_MM_1, ..., TABLE_OBSOLETE_MM_4