

2014.03.05 - Helium Polish version 5.6.32.1/report.dll 2.4.15.1/BrilRecon.dll 1.0.6.1

Release contains:

File	Version
HeliimPolish.exe	5.6.32.1
report.dll	2.4.15.1
BriRecon.dll	1.0.6.1
Reports templates	2014-03-04

This version has following new features:

1. New algorithm of building Groove for Heart cut. Please read [manual](#). This feature is protected by special license. Update keys according [standard instruction](#). Otherwise Groove method will be disabled.
2. For Heart cut we have added new type of main facets SHOULDER.

There are new bookmarks are available in report.dll version 2.4.15.1:

CROWN_FANCY_SHOULDER_ANGLE_...
CROWN_FANCY_SHOULDER_HEIGHT_...
CROWN_FANCY_SHOULDER_AZIMUTH_...
PAVILION_FANCY_SHOULDER_ANGLE_...
PAVILION_FANCY_SHOULDER_HEIGHT_...
PAVILION_FANCY_SHOULDER_AZIMUTH_...

Please find new template Full_report_for_rounded_fancies.rtf in set of templates.

1. The option Start/Main/Export c2v file... allows to collect c2v file for Helium Polish HASP key (please ensure that only one HASP key is plugged) for clients who will like to update for Heart Groove building feature.

This version has known bugs:

1. Additional contours for Groove method.
2. Rx section for search of groove projection is not optimal.
3. Not correct behavior of "Automatically delete previous models" in "Autodelete options" of Marking-out panel for model built by Groove method.