

# 2024-05-07 - HP Carbon 1.12.10

Here you can find information about what is new in HP Carbon version 1.12.10.

This version is available for [download](#) from the Octonus official web site.

On this page:

1 Algorithms of allocation

1.1 Algorithm 23. Cascade

1.2 Allocation - option "+ Brilliance based"

1.3 Improvements for algorithm of manual allocation "Change Cut To..."

2 Smart Cuts. Updates

2.1 Princess.3S.Performanceware cut

3 Seamless Technological Pipeline. Preplan concept.

3.1 Preplans segment

4 Reports improvements

4.1 Interactive features of the Remaining Depth chart

4.2 Export SVG images

4.3 I3D Mini View / I3D Report UX/UI improvements

5 Quality Control improvements and news

5.1 Quick sandwich tool

5.2 Quality Control (QC). Safe buffer of inclusions

6 User interface updates

6.1 Inclusion selection tool

6.2 Zoom/move upgrade

6.3 Interactions with diamond


7 Fixed problems and improvements

## Algorithms of allocation

### Algorithm 23. Cascade

The new algorithm 23. Cascade is available since version 1.12.10, designed for finding solutions comprising two diamonds, offers several advantages over its predecessor, the 13. Cascade-2M algorithm.

- In the search for solutions exclusively featuring the RBC cut on a large stone dataset, it operates at a speed 1.6 times faster than Cascade-2M, delivering approximately 1% more expensive solutions.
- In simultaneous execution across 10 distinct cuts, the new algorithm demonstrates a remarkable 4.5 times speed improvement and yields solutions priced approximately 1.4% higher.
- Due to a more efficient utilization of memory, the 23. Cascade algorithm can effectively handle complex diamond models with several tens of thousands of inclusions, a capability beyond the reach of 13. Cascade-2M.



### Allocation - option "+ Brilliance based"

While new global allocation algorithms prioritize finding the most price-effective solution based on a given price list, it's important to recognize that user requirements are diverse.

The value of a particular diamond to a company depends on various factors beyond its carat price alone, including:

1. The current liquidity of similar diamonds and fashion trends.
2. The diamond performance.
3. The specific preferences of the individual buyer.

4. Some customers rely on external price lists for evaluation, which are inaccessible to the algorithms.

Let's focus on the "diamond performance," specifically the Brilliance characteristic.

The program now includes Brilliance Based Cuts, which utilize a GRID-appraiser built based on the Brilliance characteristic. The preforms for these cuts undergo quality control that excludes low Brilliance and have assigned Brilliance values in the program. Modern algorithms can utilize these values.

Algorithm: 23. Single

☐ + Brilliance based

☐ + Smart Recut

Cutbook: Generic Cuts

0/65

Oval C32  
G64 P44

Oval C32  
G64 P48

Oval wBT  
P24C32

Oval WBT  
C32 G64

Oval WBT  
C32 G64

Oval WBT  
C32 G64

Oval WBT  
Shifted

Parallelepiped

Pear

Pear wBT  
P24C32

PearPro

Prince

Princess  
3s

Princess  
2S

Princess.3S\_Performanceware

Princess  
4S

Princess  
5S

Princess  
P44C44

Princess  
P52C44

Radiant

Radiant  
P28C24

Square  
Baget

Square  
Emerald

Diamond grade:  
EX


Diversity levels:  
Cut 0%  
Grade 0%  
Clarity 0%

Start Allocation

The "+ Brilliance Based" option is available in the "23. FixedForm" and "23. Single" algorithms. It allows users to obtain a range of solutions from optimal mass to optimal Brilliance. The SmartRecut algorithm is automatically launched with a single preset for all these solutions. Brilliance Based solutions are marked with shine icons in the label field. The "+ Brilliance Based" option only affects Brilliance Based Cuts

| <input checked="" type="checkbox"/> | Imported model |              | 3.9230 |  |        |           |     |   |                   |
|-------------------------------------|----------------|--------------|--------|--|--------|-----------|-----|---|-------------------|
| <input type="checkbox"/>            | 1              | Princess.... | 4465\$ |  | 1.2319 | 31.35%    | VS2 | H | VG VG EX Max_Mass |
| <input type="checkbox"/>            | 2              | Princess.... | 4758\$ |  | 1.2144 | 30.84%    | VS2 | H | EX EX EX Max_Mass |
| <input type="checkbox"/>            | 3              | Princess.... | 4719\$ |  | 1.2072 | 30.59%    | VS2 | H | EX EX EX Max_Mass |
| <input type="checkbox"/>            | 4              | Princess.... | 3803\$ |  | 1.1772 | 29.82%    | VS2 | H | EX EX EX Max_Mass |
| <input type="checkbox"/>            | 5              | Princess.... | 4758\$ |  | 1.2154 | SR 30.84% | VS2 | H | EX EX EX Max_Mass |
| <input type="checkbox"/>            | 6              | Princess.... | 4876\$ |  | 1.2401 | SR 31.61% | VS2 | H | EX EX EX Max_Mass |
| <input type="checkbox"/>            | 7              | Princess.... | 4798\$ |  | 1.2185 | SR 31.10% | VS2 | H | EX EX EX Max_Mass |
| <input type="checkbox"/>            | 8              | Princess.... | 4837\$ |  | 1.2318 | SR 31.35% | VS2 | H | EX EX EX Max_Mass |
| <input type="checkbox"/>            | 9              | Princess.... | 4876\$ |  | 1.2483 | SR 31.61% | VS2 | H | EX EX EX Max_Mass |

The option "+ Brilliance based" is disabled if no such cut is selected. **Note!** The only cut that currently supports this option is Princess.3S\_Performanceware.



To ensure the algorithms can select Brilliance Based solutions, they need to calculate them in addition to the standard solutions. This may take a bit longer, but the additional processing time is insignificant compared to the overall duration.

When searching solutions with high Brilliance, the algorithms consider the Brilliance of the preform. Notably, the "23. Single" algorithm modifies the initial preform. The SmartRecut algorithm also modifies the initial preform in both cases, including "23. FixedForm." Consequently, the algorithms can only provide an approximate estimation of the final Brilliance. We assume that solutions obtained from preforms with high Brilliance have a higher probability of achieving high Brilliance in the end.

To evaluate and compare the optical properties of the final solutions, you can use CutWise.

|                              | SCAN               | 8                  | 6                  | 9                  | 7                  | 5                  |
|------------------------------|--------------------|--------------------|--------------------|--------------------|--------------------|--------------------|
|                              |                    |                    |                    |                    |                    |                    |
|                              | 3.923ct            | 1.2483ct           | 1.2401ct           | 1.2318ct           | 1.2185ct           | 1.2154ct           |
|                              | —                  | \$4,876            | \$4,876            | \$4,837            | \$4,798            | \$4,758            |
|                              |                    |                    |                    |                    |                    |                    |
| Product SKU                  | 1deb5d48-a372-1... | 8-1deb5d48-a372... | 6-1deb5d48-a372... | 9-1deb5d48-a372... | 7-1deb5d48-a372... | 5-1deb5d48-a372... |
| Office                       |                    |                    |                    |                    |                    |                    |
| ASET                         | —                  |                    |                    |                    |                    |                    |
| Price                        | —                  | \$4,876            | \$4,876            | \$4,837            | \$4,798            | \$4,758            |
| Price Per Carat              | —                  | \$3,906/ct         | \$3,932/ct         | \$3,927/ct         | \$3,938/ct         | \$3,915/ct         |
| Carat Weight                 | 3.923ct            | 1.2483ct           | 1.2401ct           | 1.2318ct           | 1.2185ct           | 1.2154ct           |
| Shape Normalized Performance | —                  | 0.88               | 0.90               | 0.87               | 0.87               | 0.90               |
| Global Performance           | —                  | 0.88               | 0.90               | 0.87               | 0.87               | 0.90               |
| Fire                         | —                  | 0.66               | 0.70               | 0.67               | 0.60               | 0.67               |
| Brilliance                   | —                  | 0.94               | 0.95               | 0.92               | 0.94               | 0.97               |
| Optical Symmetry             | —                  | 5.96               | 6.83               | 6.89               | 7.70               | 6.97               |

There are two types of Brilliance Based solutions:

1) At the final stages of the regular algorithm, when the approximate local position of the diamond is known, the algorithm calculates additional preforms. These preforms are slightly smaller than the optimal ones in that specific position, but they have significantly better Brilliance.

Solutions obtained through this approach, after SmartRecut, can have nearly identical mass compared to the best solution or even exceed it. However, they have a significantly higher probability of achieving greater Brilliance.


2) For the combination of Cut+Grade+Clarity that has reached a sufficient price to be included in the solutions list, an additional variation of the FixedForm algorithm is launched, which uses only elite preforms.

As a result, two solutions are obtained - the solution based on the preform with the highest Brilliance and the solution with the best mass among the elite unmodified forms. These solutions do not undergo any parameter modifications until SmartRecut, which ensures their higher and more reliable Brilliance. However, their mass may be noticeably lower in the "23. Single" algorithm.




## Improvements for algorithm of manual allocation "Change Cut To..."

The "Change Cut To" menu is now available from the scene's context menu.



- Cutbook has been remastered for that command menu item and opens much faster now.
- It now features two synchronized lists with a segment for selection tabs, ensuring that the full names of the cuts are clearly visible.
- The positions of the splitter and scroll bars are remembered within the running program.
- The current cut is highlighted in dark blue, the used ones in light gray, and the one under the cursor is bordered.



## Smart Cuts. Updates


### Princess.3S.Performanceware cut

Cut Princess.3S\_Performanceware is implemented on the base of cut Princess.3S. This is the first cut that works with the "Brilliance based" technology, see above.

# Seamless Technological Pipeline. Preplan concept.

## Preplans segment

Preplans are separated into a single section in the solutions list. The 'Cut' column will indicate 'Preplan' for them.



# Reports improvements

## Interactive features of the Remaining Depth chart


In the I3D Report, implemented interactive features within the Remaining Depth chart.

Users can now easily toggle the visibility of associated lines and marks by clicking on the respective legend items. Selections are saved and persist across program relaunches, providing a seamless experience.


This update introduces a more intuitive and dynamic interaction, allowing users to focus on specific lines of data that are of interest.

By default, only the Max Line (Blue) is enabled, while Girdle Zone Min and Max are disabled.

Sample: [Plan+Preplan+Bruted.ox2z](#)




Introduced an "Info" button to display an image containing graphical explanations of distances on the chart. The image updates based on the selection made in the legend items.



## Export SVG images

In Export Report Data, the capability to export images in the SVG (Scalable Vector Graphics) format has been introduced. This format offers high-quality vector images that can be scaled to any size without loss of quality.



Additionally, the image format for export can now be configured in the General Settings dialog.

Settings

Page Filter

General

Scanning

Automatic Actions

Reports

Reports

General

Report Buttons

Interactive 3D Reports

Viewers path: %ProgramData%\OctoNus Software\I3D Report Viewer

Data path: %MyDocuments%\OctoNus Software\I3D Reports

Browser executable path: C:\Program Files\Google\Chrome\Application\chrome.exe

☒ Use default system browser

☐ Add photorealistic images to report

☒ Automatically open report in browser

Interactive I3D Mini View

Web Pages Count Limit: 16

Export Report Data

Export image formats:

☒ SVG

☒ PNG


☒ EMF

OK Cancel Apply

I3D Mini View / I3D Report UX/UI improvements

In the I3D Mini View / Report, the quality of UX/UI has been improved, specifically:

- the zoom works without modifiers, just with the mouse wheel, and the strength factor of zoom buttons has increased
- navigation buttons have been moved up for quick access
- the empty space between the scene and the table has been eliminated



Quality Control improvements and news


Quick sandwich tool

A quick sandwich tool has been added, which makes it possible to separate a smaller peace of inclusion. This may increase plan weight with the same clarity. Please look at the video with demo of tool advantages and settings:

| Video   Quick Sandwich - Tool to separate part of inclusion                                                                                                                                                                                                                                                                                                                                                                                             |                         |                                               |              |       |
|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-------------------------|-----------------------------------------------|--------------|-------|
| Published:                                                                                                                                                                                                                                                                                                                                                                                                                                              | 2024, February 16       | Last Updated:                                 | 2024, June 5 | v.4.8 |
| Your browser does not support the HTML5 video element                                                                                                                                                                                                                                                                                                                                                                                                   |                         |                                               |              |       |
| <b>Video summary:</b> <ul style="list-style-type: none"><li>• Splitting inclusions into parts, known as "sandwich", may increase plan weight with the same clarity.</li><li>• The quick sandwich cuts a small part from the inclusion with parallel to the diamond plane. There are preset offset values with the expected clarity of the separated part.</li><li>• This tool gives you an opportunity to significantly improve the solution.</li></ul> |                         |                                               |              |       |
| <b>Video keywords:</b> sandwich, inclusion, separation tool                                                                                                                                                                                                                                                                                                                                                                                             |                         |                                               |              |       |
| Data                                                                                                                                                                                                                                                                                                                                                                                                                                                    | raw_diamond_sample.ox2z |                                               |              |       |
| Published in:                                                                                                                                                                                                                                                                                                                                                                                                                                           | Release Notes           | 2024-05-07 - HP Carbon 1.12.10                |              |       |
|                                                                                                                                                                                                                                                                                                                                                                                                                                                         | Documentation           | NA                                            |              |       |
|                                                                                                                                                                                                                                                                                                                                                                                                                                                         | Playlists               | NA                                            |              |       |
|                                                                                                                                                                                                                                                                                                                                                                                                                                                         | Also                    | As Separate Page   On YouTube   Specification |              |       |

The quick sandwich tool is available in two places:

- the scene's context menu



- the inclusion list

Plan 1

|                                     | Diam # | Cut       | Price  | Discount | PPC          | Mass     | Clarity | DZ | Grade |
|-------------------------------------|--------|-----------|--------|----------|--------------|----------|---------|----|-------|
| <input checked="" type="checkbox"/> | Diam 1 | Brilliant | 9557\$ | -35%     | 5655.00\$/ct | 1.6911ct | VS2     | H  | EX    |

Inclusions (30 of 186)

☒ QC Filter

Clarity: IF VVS1 VVS2 VS1 VS2 SI1 SI2 SI3 I1 I2 I3

Diamond: #1 ☐ inside ☒ outside 0 5 10 20 50 100 200 500 1000 off 200µm

|             |  |     |                                     |
|-------------|--|-----|-------------------------------------|
| 3D-5        |  | SI1 |                                     |
| 3D-7 N Jalu |  | SI2 | <input checked="" type="checkbox"/> |
| 3D-9        |  | SI2 | <input type="checkbox"/>            |
| 3D-15       |  | I1  | <input type="checkbox"/>            |
| 3D-17       |  | SI1 | <input type="checkbox"/>            |
| 3D-21       |  | SI1 | <input type="checkbox"/>            |
| 3D-22       |  | SI1 | <input type="checkbox"/>            |
| 3D-23       |  | I1  | <input type="checkbox"/>            |
| 3D-25       |  | I1  | <input type="checkbox"/>            |
| 3D-26       |  | I1  | <input type="checkbox"/>            |
| 3D-28       |  | VS2 | <input type="checkbox"/>            |
| 3D-29       |  | VS1 | <input type="checkbox"/>            |
| 3D-34       |  | VS2 | <input type="checkbox"/>            |

Appraiser

Diamond Allocation

Algorithm: 23. Single Cutbook: Brilliant

Brilliant

Brilliant

Safe buffer (14 µm)

Safe buffer...

Safe buffer 10 µm

Safe buffer 20 µm

Safe buffer 30 µm

Safe buffer 40 µm

Safe buffer 50 µm

Safe buffer 100 µm

Remove Safe buffer

Delete Inclusion

Manual appraiser selection

Diamond grade: EX

Diversity levels: Cut 20% Grade 10% Clarity 5%

Start Allocation

Additionally, there is an option to apply the quick sandwich to all inclusions near the active diamond.

Plan 1

|                                     | Diam # | Cut       | Price  | Discount | PPC          | Mass     | Clarity | DZ | Grade |
|-------------------------------------|--------|-----------|--------|----------|--------------|----------|---------|----|-------|
| <input checked="" type="checkbox"/> | Diam 1 | Brilliant | 9557\$ | -35%     | 5655.00\$/ct | 1.6911ct | VS2     | H  | EX    |

Inclusions (30 of 186)

☒ QC Filter

Clarity: IF VVS1 VVS2 VS1 VS2 SI1 SI2 SI3 I1 I2 I3

Diamond: #1 ☐ inside ☒ outside 0 5 10 20 50 100 200 500 1000 off 200µm

|             |  |     |                                     |
|-------------|--|-----|-------------------------------------|
| 3D-5        |  | SI1 |                                     |
| 3D-7 N Jalu |  | SI2 | <input checked="" type="checkbox"/> |
| 3D-9        |  | SI2 | <input type="checkbox"/>            |
| 3D-15       |  | I1  | <input type="checkbox"/>            |
| 3D-17       |  | SI1 | <input type="checkbox"/>            |
| 3D-21       |  | SI1 | <input type="checkbox"/>            |
| 3D-22       |  | SI1 | <input type="checkbox"/>            |
| 3D-23       |  | I1  | <input type="checkbox"/>            |
| 3D-25       |  | I1  | <input type="checkbox"/>            |
| 3D-26       |  | I1  | <input type="checkbox"/>            |
| 3D-28       |  | VS2 | <input type="checkbox"/>            |
| 3D-29       |  | VS1 | <input type="checkbox"/>            |
| 3D-34       |  | VS2 | <input type="checkbox"/>            |

Create quick sandwiches for inclusions near the active diamond (#1 Brilliant 1.6911ct)...

Remove sandwiches

Safe buffer around diamond #1 Brilliant 1.6911ct

Safe buffer (14 µm)

Safe buffer...

Safe buffer 10 µm

Safe buffer 20 µm

Safe buffer 30 µm

Safe buffer 40 µm


Safe buffer 50 µm

Safe buffer 100 µm


Remove Safe buffers

Remove inclusions outside the scan (Imported model)

For detailed customization, a modal window can be opened to input the desired offset.



The result of the quick sandwich applying is an separated inclusion with parallel to the diamond plane.



Quality Control (QC). Safe buffer of inclusions


- Added context menu to scene.
- Unified Safe buffer elements in all menus (in the scene, list, and panel header).

| in the scene                                                                |                                                                                                                                                                                                                                                            |                                                                                                                                                                                                                                                                                      |                                                                                                                                                                                                                                                                                                                              |                                                                                                                                                                                                                                                                                        | in the list                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                               | in the panel header                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                                 |
|-----------------------------------------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <div>Planes</div> <div>Plane from points</div> <div>Plane from facets</div> | <div>XRayAuto-3</div> <div>IF</div> <div>VVS1</div> <div>VVS2</div> <div>VS1</div> <div>VS2</div> <div>SI1</div> <div>SI2</div> <div>SI3</div> <div>I1</div> <div>I2</div> <div>I3</div> <div>Green</div> <div>Yellow</div> <div>Red</div> <div>Grey</div> | <div>Quick Sandwich "#2.0 0.33ct"</div> <div>Quick sandwich 40 µm</div> <div>Quick sandwich...</div> <div>14 µm VVS1</div> <div>20 µm VVS2</div> <div>34 µm VS1</div> <div>68 µm VS2</div> <div>136 µm SI1</div> <div>224 µm SI2</div> <div>380 µm I1</div> <div>Undo sandwich</div> | <div>XRayAuto-3</div> <div>#2 Brilliant 0.3364ct</div> <div>Safe buffer (75 µm)</div> <div>Safe buffer...</div> <div>Safe buffer 10 µm</div> <div>Safe buffer 20 µm</div> <div>Safe buffer 30 µm</div> <div>Safe buffer 40 µm</div> <div>Safe buffer 50 µm</div> <div>Safe buffer 100 µm</div> <div>Remove Safe buffer</div> | <div>Cavity-inclusion</div> <div>Instant Cavity</div> <div>(depth: 100 µm, raduis: 100 µm)</div> <div>Cavity...</div> <div>Instant Cavity 10 µm</div> <div>Instant Cavity 20 µm</div> <div>Instant Cavity 30 µm</div> <div>Instant Cavity 50 µm</div> <div>Instant Cavity 100 µm</div> | <div>Inclusion Status</div> <div>Green Status</div> <div>Yellow Status</div> <div>Red Status</div> <div>Grey Status</div> <div>Inclusion Clarity</div> <div>Change Clarity...</div> <div>Sandwich</div> <div>Make Sandwich...</div> <div>Quick Sandwich...</div> <div>XRayAuto-3</div> <div>#2 Brilliant 0.3364ct</div> <div>Safe buffer (75 µm)</div> <div>Safe buffer...</div> <div>Safe buffer 10 µm</div> <div>Safe buffer 20 µm</div> <div>Safe buffer 30 µm</div> <div>Safe buffer 40 µm</div> <div>Safe buffer 50 µm</div> <div>Safe buffer 100 µm</div> <div>Remove Safe buffer</div> <div>Delete Inclusion</div> | <div>Create quick sandwiches for inclusions near the active diamond (#2 Brilliant 0.3364ct)...</div> <div>Remove sandwiches</div> <div>Safe buffer around diamond #2 Brilliant 0.3364ct</div> <div>Safe buffer (75 µm)</div> <div>Safe buffer...</div> <div>Safe buffer 10 µm</div> <div>Safe buffer 20 µm</div> <div>Safe buffer 30 µm</div> <div>Safe buffer 40 µm</div> <div>Safe buffer 50 µm</div> <div>Safe buffer 100 µm</div> <div>Remove Safe buffers</div> <div>Remove inclusions outside the scan (Imported model)</div> |

User interface updates

## Inclusion selection tool

Now the selection with inclusion can be removed.  
For that purposes, you need to click on an empty space in the scene with the inclusion selection tool active.  
Also, for convenience, you can use the SHIFT modifier instead of the tool on the panel.




## Zoom/move upgrade

Zoom has significantly improved:

- On the 3D scene, the zoom targets the area under the cursor, if there is a diamond underneath.
- On 2D it simply zooms under the cursor.


On the 2D scene, you can move around using the combination 'Left click + SHIFT + Mouse Move'.  
Additionally, the scroll bars that appear when zooming in can be disabled in the menu item View -> Show Scroll Bars.




By double-clicking on the scene, you can reset all transformations (zoom and movements) made with the mouse.

# Interactions with diamond


Diamond facets and edges are highlighted upon mouse hover.




This feature is disabled by default, so you need to click on View -> Enable bone highlighting / Enable facet highlighting accordingly.




When the feature is enabled, some commands are available in the scene's context menu:



- Set the orientation of the diamond by facet
- Create a bounding plane by facet or edge
- Create a sawing plane by facet or edge




Since it's now possible to manually set sawing planes, we've added the ability to modify and delete them.








## Fixed problems and improvements

- Excluded the usage of Stone ID for file names in Cutwise export packages due to compatibility issues with the Cutwise server unpacker.
- Fixed the issue of the 'Upload to Cutwise' button remaining inactive when opening a new project before obtaining a link to an uploaded project.


- Aqua preplans are now considered in the Recognition process in HP Carbon.
- Fixed an issue where Automatic actions or Report Buttons' actions were unintentionally triggered for all shapes when the current shape is AnyCut.



- The algorithm for calculating Remaining Depth Blue Line has been reworked. This fixed critical bugs in the old implementation. The purple line in the figure shows the behavior of the new version of the algorithm compared to the old one.




- For all cutting types, when dealing with asymmetrical cuts featuring an unsmooth girdle, illustrations depicting symmetry show facets with their angles and girdle lengths, while symmetry axes are omitted.




Bookmarks for images:  
"PLOT\_ACTUAL\_LENGTH\_AXIS\_ASYM";  
"PLOT\_ACTUAL\_LENGTH\_AXIS\_ASYM\_CROWN";  
"PLOT\_LENGTH\_AXIS\_SYM\_COR";  
"PLOT\_LENGTH\_AXIS\_SYM\_COR\_CROWN";  
"PLOT\_ACTUAL\_WIDTH\_AXIS\_ASYM";  
"PLOT\_ACTUAL\_WIDTH\_AXIS\_ASYM\_CROWN";  
"PLOT\_WIDTH\_AXIS\_SYM\_COR";  
"PLOT\_WIDTH\_AXIS\_SYM\_COR\_CROWN";  
"PLOT\_BOTH\_AXES\_SYM\_COR";  
"PLOT\_BOTH\_AXES\_SYM\_COR\_CROWN";

These parameters are also outputted to separate bookmarks: angles in GIRDLE\_INTERNAL\_ANGLE\_DEG\_..., and lengths in GIRDLE\_SIDE\_LENGTH\_MM\_...

- Fixed sawing preplan creation for solutions with multiple sawing layers.  
Previously, the consideration of all sawing layers was incomplete; now, it has been fixed.



- Added the "Crown + Pavilion" option in G1 Blocking mode. Additionally, aligned the process of creating blocking preplans with the faceting stages, enabling separate preplan creation for Crown, Pavilion, as well as Crown + Pavilion.



- Fixed rare program crashes during
  - Facet Marking transfer to semipolished model;
  - MEC algorithm
  - SmartRecut algorithm in streaming mode