

2014.08.14 - Helium Polish version 5.6.51.1/brilrecon.dll version 1.0.17.1

Release contains:

File	Version
HeliimPolish.exe	5.6.51.1
BriRecon.dll	1.0.17.1

In this version we make following changes:

1. Improvement of CUSHION model building.
2. Improvement of cavity search on models (near culet and in other places of model). We noticed that in previous versions some cavities were missed on models (especial near culet), which are present in real stone. In this version they are built.
3. We improve algorithm of flip search – we recently found some instability in search of flip (more than 0,1 pix dispersion between several measurements during calibration from Tune hardware panel). Also during tuning we recommend to use 100 as number of images during search of flip value. We are still testing this version for flip issue.