
DiBox Inclusions



- 1. Load or create project and select stone contour
- 2. Load .dmc or .gem model with stone model (use Ctrl+D shortcut on Edit tab) a. Stone diagram is visible when inclusions tools are selected



b. Adjust rotation angle with Angle control



c. Use Show model checkbox to display diamond model over photo



- 3. Manual inclusion tool (same as stone contour tool)
 - a. Left click to start inclusion
 - b. Left click to add vertices\right click to remove vertices\ click and drag to move vertex
 - c. Press Enter to add inclusion or Esc to cancel
 - d. Click on inclusion to select it
 - i. Press delete button to remove inclusion
 - ii. Edit inclusion
 - iii. Press *Enter* to confirm editing



- 4. Marker inclusion tool
 - a. Left click to start inclusion draw inclusion with left button pressed
 - b. Brush size can be adjusted with '[' and ']' buttons
 - c. Alt + left button to erase inclusion
 - d. Press *Enter* to add inclusion or *Esc* to cancel



- 5. Magic Wand inclusion tool
 - a. Left mouse button to mark inclusion (just draw some area in the middle of inclusion)
 - b. Brush size can be adjusted with '[' and ']' buttons
 - c. Alt + left mouse button to mark background
 - d. Press Enter to add inclusion or Esc to cancel
- 6. Every selected image will be exported with and without inclusions. There will be separate diagram image with inclusions.

