


**2016.06.28 - Helium Polish: version 5.6.88.1, report.dll version 2.9.7.1, report templates dd 12.07.2016**

Release contains:


| File              | Version    |
|-------------------|------------|
| HeliumPolish.exe  | 5.6.88.1   |
| report.dll        | 2.9.7.1    |
| Reports templates | 2016-07-12 |

In this version we made the following changes:


1. Culet Center calculation algorithm for steps cuts was **updated**:



2. Girdle Center calculation for Cushion was **updated** to become consistent with that for Oval. So from now on, Girdle Center and Girdle Center Mass for Cushion are not the same.



3. Illustrative report for 10 hearts RBC was **added**:



All parameters from Illustrative report were adapted for RBC 10x hearts. Small Bezel slope is indicated on the pictures.