


2016.06.28 - Helium Polish: version 5.6.88.1, report.dll version 2.9.7.1, report templates dd 12.07.2016

Release contains:


File	Version
HeliumPolish.exe	5.6.88.1
report.dll	2.9.7.1
Reports templates	2016-07-12

In this version we made the following changes:


1. Culet Center calculation algorithm for steps cuts was **updated**:



2. Girdle Center calculation for Cushion was **updated** to become consistent with that for Oval. So from now on, Girdle Center and Girdle Center Mass for Cushion are not the same.



3. Illustrative report for 10 hearts RBC was added:



All parameters from Illustrative report were adapted for RBC 10x hearts. Small Bezel slope is indicated on the pictures.