


Reports

On this page:	
1	Overview
2	Report Folders and Files

Overview

The reports are accessible via the right panel.




Standard report opens a special panel to view the report within HPOxygen. The remaining options imply the usage of external programs and are grouped under the **Export** section, which includes:

- **Polish Report**, also accessible via **File - Create polished report**; includes RTF, HTML, and [Interactive 3D](#) reports;
- **Custom report** with user-defined facet marking;
- **Comparative Report** (note that this option is not visible in the **Scan** mode, and becomes enabled once you have selected exactly two models in the **Allocation solutions** panel);
- **Print Label**;
- **Export Report Data - Color**.

See the corresponding sections for more details.

Report Folders and Files


For most reports, paths and file names are the following:



Polish Reports. Now when you click on the right panel, the **Polish Report**, then, in the **Report templates** section,

- click the **Open RTF** tab, select the template and run the report, the generated RTF file will be automatically saved as:
...\\Documents\\OctoNus Software\\Polish Reports\\RTF**Project Name\\XXXX\\XXXX-Project Name-report.rtf**

For example, if you run Polish report 3 times for the "Oval_blocked_001_ver2.oxgz", you will obtain:



- If you select the **Open HTML** tab:
...\\Documents\\OctoNus Software\\Polish Reports\\HTML**Project Name\\XXXX**files of the report .

