Video | AnyCut Workflow - Main Steps

Video AnyCut Workflow - Main Steps					
Published:	2019, September 3	Last Updated:	2019, October 16	v.2.3	
Your browser does not support the HTML5 video element					

Video summary:

- AnyCut workflow includes the following steps: User cutting registration, FixedForm (recut) allocation, SmartRecut AnyCut allocation with relative ASCII appraiser
 User cutting registration starts from running SmartNormilize for the model you want to use as cutting
 Register most symmetrical normalization result as new cutting
 Provide Custom Facet Marking for your new cutting

- Provide Custom Facet Marking for your new cutting
 Facet Marking from a sample can be used
 If necessary, corrections may be done for selected marking from sample
 Save your cutting
 Run FixedForm (recut) allocation with your cutting
 Use + Smart Recut option to immediately start SmartRecut after the Recut
 The system provides a set of solutions

Video keywords: AnyCut, user cutting, custom facet marking, SmartRecut

Published in:	Release Notes	2019-09-13 - HPOxygen Server 5.2.22	
	Documentation	AnyCut Workflow, User Cutting Registration	
	Playliss	All Videos	
	Also	As Separate Page Specification	

