How to use DM software in the interlaced stereo mode

The following settings are located in the **NVIDIA Control Panel**. To open the panel you should click right mouse button on the desktop and select the appropriate option from the context menu. Also you can find it in the **Control Panel**.

If you want to use DM application over the 3D TV with interlaced stereo (passive glasses), please follow these steps.

Step-by-step guide

Disable stereoscopic 3D (NVIDIA GeForce/Quadro)

- 1. Click on the Set up stereoscopic 3D (Stereoscopic 3D section from the left side);
- 2. Uncheck Enable stereoscopic 3D;
- 3. Click on the Apply button.

Disable windowed stereo (NVIDIA Quadro only)

- 1. Click on Manage 3D settings (3D Settings section from the left side);
- 2. Click on Stereo Enable and select Off (only for DM software or in the Global Settings section);
- 3. Click on the Apply button.

After that, if you run the **DM** application, it will be started with supporting of the interlaced stereo.



Notes:

- For scaling the frame, activate the **Image Fit Mode** (Alt + T).
- If the **DM** GUI font size is too small for the current display resolution (for example, when you use **Ultra HD 4K**), or the GUI text is difficult to read in the interlaced stereo mode, please activate the bold font in the application (for details see: How to activate bold font in the DM software GUI).

Related articles

- How to use DM software without MBox hardware
- How to use DM software with PointGrey cameras
- Copying configuration from the old DM version
- How to use DM software with GT1660 cameras
- How to capture RAW snapshot